

SOFTWARE INFORMATION

BZDM-7020/7720 V3.23 for DME-7000

Product: **BZDM-7020, BZDM-7720, DME-7000**

Serial No: **All**

DESCRIPTION

BZDM-7020/7720 Operating Software V3.23 for the DME-7000 has now been released. This software supersedes V3.22.

IMPROVEMENTS

The following conditions have been corrected:

1. Cross-point was not switched when Effect or Snapshot of the DME unit was recalled from the shot box.
2. Multi Pause did not work correctly when the unit was connected to a DVS-7000.

INSTALLATION PROCEDURE

Caution: All effects, snapshots and setup data will be erased by installing this software. Therefore, it is recommended that all data is saved to floppy disk before starting the installation so that it can be restored afterwards.

1. Install DME-7000 System Disks 1 and 2 as described in Section 10 of the BZDM-7020 User's Guide.
2. If a BKDM-7031 sparkle option board is installed, re-install the BKDM-7031 software.
3. If a BKDM-7041 sketch option board is installed, re-install the BKDM-7041 software.

CONFIRMATION PROCEDURE

Confirm the versions are correct in page 723 of the Version menu.

DME -7000 V3.23 R04.05	(C) SONY Wed Oct 22 16:15:02 2003
BZDM-7010/20 V3.23	(C) SONY Fri Sep 24 10:00:00 2003
BKDM-3030 V1.41 R05.03	
BKDM-3040 V3.00 R06.01	
BKDM-7031 V1.11 R05.03	
BKDM-7041 V3.01 R06.01	
BKDM-7070 V3.11 R06.16	

SOFTWARE SET CONTENTS

- This document
- Floppy disk (DME-7000 SYSTEM DISK 1/2, V3.23)
- Floppy disk (DME-7000 SYSTEM DISK 2/2, V3.23)
- Your licence agreement for the software